

MSE200

Lecture 19 (CH. 11.6, 11.8)

Ceramics

Instructor: Yuntian Zhu

Objectives/outcomes: You will learn the following:

- Mechanical properties: Deformation mechanism, strength, toughness, Transformation toughening, Fatigue.
- Glasses: The glass transition temperature. Structure of glass. Network formers, modifiers, and intermediates. Mechanical properties of glass. Strengthening of glasses by tempering and chemical treatment

Mechanical Properties of Ceramics


- Ceramics are generally brittle.
- Tensile strength is lower than compressive strength.
- Toughness is the most important parameter

Material	Density (g/cm ³)	Compressive strength		Tensile strength		Flexural strength		Fracture toughness	
		MPa	ksi	MPa	ksi	MPa	ksi	MPa√m	ksi√m
Al ₂ O ₃ (99%)	3.85	2585	375	207	30	345	50	4	3.63
Si ₃ N ₄ (hot-pressed)	3.19	3450	500	690	100	6.6	5.99
Si ₃ N ₄ (reaction-bonded)	2.8	770	112	255	37	3.6	3.27
SiC (sintered)	3.1	3860	560	170	25	550	80	4	3.63
ZrO ₂ , 9% MgO (partially stabilized)	5.5	1860	270	690	100	8+	7.26+

Comparison: Steel usually have a strength of 500 -1000 MPa

Mechanism of deformation: Covalently bonded ceramics

- Brittle fracture due to separation of electron-pair bonds




Ionically bonded ceramics

- Single crystal show considerable plastic deformation under compression
- Polycrystalline ceramics are brittle

• **Example:** NaCl crystal

- Slip in **{100}** family of planes is rarely observed as same charges come into contact.
- Cracking occurs at **grain boundaries**.



Factors Affecting Strength


- Failure occurs mainly from **surface defects**.
- Pores gives rise to **stress concentration** and cracks.
- Finer size ceramics have smaller flaws and hence are stronger.
- **Composition, microstructure, surface condition, temperature and environment** also determine strength.

The strength of ceramics is usually determined by the largest flaw

Toughness of ceramic Materials

- Ceramics have **low strength**
- Improving toughness is most important
- K_{IC} values (toughness) obtained by *four point bend test*.

$$\underline{K_{IC} = Y\sigma_f \sqrt{\pi a}}$$



σ_f = fracture stress (MPa)

a = half size of target internal flaw

Y = dimensionless constant

Size effect

$$K_{IC} = Y\sigma_f \sqrt{\pi a} \quad \rightarrow \quad \sigma_f = \frac{K_{IC}}{Y\sqrt{\pi a}}$$

K_{IC} is a material value, and can be usually regarded as a constant for the same ceramic material


- Larger parts has a higher probability of containing a larger flaw
- Larger parts are likely to have a lower strength

Transformation Toughening of Partially Stabilized ZrO₂

- Transformation of Zirconia combined with some other refractory oxides (MgO) can produce **very high toughness ceramics**.
- ZrO₂ exists in 3 structures.
 - **Monoclinic** → Up to 1170°C
 - **Tetragonal** → 1170 – 2370°C
 - **Cubic** → above 2370°C
- Adding 10% mol of MgO **stabilizes** cubic form so that it can exist in metastable state in room condition.


Toughness of Zirconia (Cont..)

- If a mixture of **ZrO₂ – 9 mol% MgO** is sintered at about 1800°C and rapidly cooled, it will be in metastable state.
- If reheated to 1400°C and held for sufficient time **tetragonal structure precipitates.**
- Under action of stress, this tetragonal structure **transforms to monoclinic increasing volume** and hence retarding crack growth.




Glasses

- **Combination of transparency, strength, hardness and corrosion resistance.**
- **Glass is an amorphous ceramic material**
- **Up on cooling, it transforms from rubbery material to rigid glass.**



Structure of Glasses

- Fundamental subunit of glass is **SiO_4^{4-} tetrahedron**.
- Si^{4+} ion is covalently ionically bonded to four oxygen atoms.
- In **crystalite**, Si-O tetrahedra are joined corner to corner to form **long range order**.
- In **simple silica glass**, tetrahedra are joined corner to corner to form **loose network**.



Glass Modifying Oxides and Intermediate Oxides

- **Network modifiers:** Oxides that **breakup** the glass network.
 - Added to glass to increase workability.
 - **Examples:-** Na_2O , K_2O , CaO , MgO .
 - Oxygen atom enters network and other ion stay in interstices.
- **Intermediate oxides:** Cannot form glass network by themselves but can **join** into an existing network.
 - Added to obtain special properties.
 - **Examples:** Al_2O_3 , Lead oxide.

Composition of Glasses

- **Soda lime glass:** Very common glass (90%).
 - 71-73% SiO_2 , 12-14% Na_2O , 10-12% CaO .
 - Easier to form and used in flat glass and containers.



Borosilicate glass

Alkali oxides are replaced by boric oxide in silica glass network.


- Known as **Pyrex glass** and is used for lab equipments and piping.



Lead glass

Lead oxide acts as network modifier and network former.

- **Low melting point – used for solder sealing.**
- **Used in radiation shields, optical glass and TV bulbs.**



Viscous Deformation of glasses.


- Viscous above T_g and viscosity **decreases** with increase in temperature.

$$\eta^* = \eta_0 e^{+Q/RT}$$

Q = Activation energy

η^* = Viscosity of glass (PaS)



η_0 = preexponential constant (PaS)



1. **Working point:** 10^3 PaS – glass fabrication can be carried out
2. **Softening point:** 10^7 PaS – glass flows under its own weight.
3. **Annealing point:** 10^{12} PaS – Internal stresses can be relieved..
4. **Strain point:** $10^{13.5}$ PaS – glass is rigid below this point.

Forming Methods


- **Forming sheet and plate glass:**
Ribbon of glass moves out of furnace and floats on a **bath of molten tin**.
- **Glass is cooled by molten tin.**
- **After it is hard, it is removed and passed through a long **annealing furnace**.**



<http://video.google.com/videosearch?q=glass+blowing&hl=en&sitesearch=>

Blowing, Pressing and Casting

- **Blowing:** Air blown to force molten glass into molds.
- **Pressing:** Optical and sealed beam lenses are pressed by a **plunger** into a mold containing molten glass.
- **Casting:** Molten glass is cast in open mold.
- **Centrifugal casting:** Glass globs are dropped into spinning mold.
- Glass first flows outward towards wall of mold and then **upward** against the mold wall.



Tempered Glass

- Glass is heated into near softening point and **rapidly cooled**.
- Surface cools first and **contracts**.
- Interior cools last and contracts causing **tensile stresses** in the interior and **compressive stress** on the surface.
- Tempering strengthens the glass.
- **Examples:** Auto side windows and safety glasses.




Figure 10.58

Chemically Strengthened Glass

- Special treatment increases **chemical resistance** of glasses.
- **Example:-** Sodium aluminosilicate glasses are immersed in a bath of potassium nitrate at 50⁰C for 6 to 10 hours
 - Large potassium ions are induced into surface causing **compressive stress**.
 - Compressive layer is much **thinner** than that in thermal tempering.
 - Used for supersonic aircraft glazing and **ophthalmic lenses**.

HW

- **Chapter 11: 22, 23, 25, 26,**
- **Example problems: 11.1, 11.2, 11.3, 11.4, 11.5, 11.6, 11.7, 11.8, 11.9, 11.10**